



# User Manual

# MDSEC

## Application Security Tool for the IBM i from Midrange Dynamics

Version 8.1.2  
Published August 26, 2018



## MDSEC - Table of Contents

1	OVERVIEW .....	3
1.1	Terminology .....	3
1.2	Starting MDSEC.....	4
1.3	MDSEC Menu .....	4
2	USER ROLES .....	6
2.1	User Role Listing.....	6
2.2	MDSEC Application Levels for Role.....	8
2.3	MDSEC Security Codes for Role .....	9
2.4	MDSEC Code Limits for Role .....	11
2.5	Users with Role .....	12
3	USERS.....	13
3.1	User Listing.....	13
3.2	Roles for User .....	16
4	FUNCTIONAL SECURITY CODES .....	18
4.1	Application Level Listing .....	18
4.2	Application Code Listing.....	20
5	EMBEDDING MDSEC INTO YOUR APPLICATIONS .....	21
5.1	MDSECAUT Parameter Table.....	21
5.2	Detailed Description of MDSECAUT Parameters.....	21
5.3	Programming Examples and Copybooks .....	22
6	MD COMMAND SECURITY .....	23
7	MDSEC REPORT GENERATOR.....	24
7.1	Role Authority .....	25
7.2	User Authority.....	27
7.3	Users with Role .....	29
7.4	Roles for User .....	30
7.5	Report Output.....	31
7.6	MDRUNRPT – Run Report command.....	32
7.7	MDEXPSPLF – Export Spooled File command.....	34
8	AUTHORIZATION LISTS .....	36
8.1	Listing of Authorization Lists .....	36
8.2	Authorization List Maintenance .....	37
8.3	Authorization List User Maintenance .....	38
9	DDM SECURITY .....	39
9.1	Overview .....	39
9.2	General Configuration.....	39
9.3	Data Filters.....	41
9.4	User Filters .....	41
10	SYSTEM SETTINGS .....	42
10.1	Setting the JVM to be used for MD Java Modules .....	43
11	EMAIL SETTINGS.....	44
11.1	Email Addresses.....	45
11.2	Email Log.....	46
	<b>APPENDIX A – STANDARD USER ROLES .....</b>	<b>47</b>
	<b>APPENDIX B – MD PRODUCT SECURITY CODES.....</b>	<b>48</b>

## 1 Overview

The MDSEC Application-Security tool provides IT staff a user-friendly means to secure MDCMS, MDOpen, MDXREF and MDWorkflow, as well as their in-house applications, at a functional and object level. Security administrators then have a simple means to manage user authorities for application functions as well as easy management of IBMi authorization lists and DDM usage.

### 1.1 Terminology

#### Application

An application is a collection of functional security codes. MD product application codes are automatically opened in MDSEC and contain all security codes for the authorization to MDCMS and MDXREF functions. Application **md** contains the default and general authorizations for the MD products.

Additionally, applications can be created in MDSEC to manage the authorizations to in-house functions.

#### Level

The level represents an instance, or environment, of an application (development, test, production, etc.). The general application **md** doesn't contain levels, but each MDCMS/MDXREF level defined for an organization can have certain security functions limited to specific levels for a given user.

#### Code

The application code is a security code that represents a function that requires authorization within MDSEC. Codes for MDCMS and MDXREF are between 0 (general access) and 99. In-house codes for applications used in MDCMS or MDXREF are 100 or higher. Codes for in-house applications are 0 or higher.

In-house codes can also use limits so that a user only has authority when the run-time value being checked against is within the allowed limits.

#### User Role

A user role is a collection of authorities. When a role is granted authority to 1 or more codes, every user having the role is automatically granted the same authority to those codes.

A user may belong to multiple roles, thus having authority to all codes granted to each role that the user belongs to.

The standard list of User Roles and an overview of their default capabilities is available in Appendix A.

#### User

A user is a profile that exists on the IBMi system that should have authority to one or more application codes based on role memberships and personally granted authorities.

## 1.2 Starting MDSEC

Type the command MDSEC from a command line. If using a suffix for a separate instance of MDSEC, then enter that value in the ENV parameter. For example, MDSEC ENV(XXXX).

MDSEC may also be accessed from the MDCMS Settings Menu option #8.

A user will only be able to view the current settings in MDSEC unless that user has either \*SECOFR authority, \*SECADM authority or has been granted security privileges within MDSEC.

## 1.3 MDSEC Menu

The Main menu for MDSEC. If the user does not have administration rights within MDSEC, then the menu will not be displayed and the user will automatically be shown the User listing screen.

```

SCLMENU                                Company Name                                9.03.10
SCRN1                                  MDSEC Main Menu                                14:04:57

      Opt  Description
      1    User Roles
      2    Users
      3    Functional Security Codes
      4    Authorization Lists
      5    DDM Security
      6    MD Command Security
      7    Report Generator

      9    License Keys

     11    System Settings
     12    Email Settings

      Selection: __

F3=Exit  F6=Messages  F8=Submitted Jobs  F11=Output  F21=Sys Command
  
```

### Option 1: User Roles

Manages the list of User Roles that have functional access to MDCMS, MDXREF, or in-house applications.

### Option 2: Users

Manages the list of user profiles that have functional access to MDCMS, MDXREF, or in-house applications through user roles or personal authorities.

### Option 3: Functional Security Codes

Manages the list of functional security codes to be used to secure in-house applications.

### Option 4: Authorization Lists

Manages the authorization lists on the system as well as the user rights for users belonging to those lists.



Option 5: DDM Security

Manages the access rights and logging of DDM (Distributed Data Management) transactions. This option is only available from the default instance of MDSEC.

Option 6: MD Command Security

Grants or Revokes permissions to execute MD commands that cause updates to MDCMS data or deployments.

Option 7: Report Generator

Allows the user to generate a variety of security reports for Users and Roles.

Option 9: License Keys

Allows for the update of the MD license keys in case the previous keys need to be adjusted or a new MD product license is to be added.

Option 11: System Settings

Defines various system-wide information for this instance of the MD Products.

Option 12: Email Settings

Defines the SMTP credentials and the list of recipient email addresses.



## 2 User Roles

### 2.1 User Role Listing

Option 1 from MDSEC Menu: all roles that are currently defined within MDSEC.

```

SCCGPD                               Company Name          9.12.16
SCRN1                                MDSEC User Roles    10:37:00

Filter by Desc: _____      Appl: _____
Pos: _____                 User: _____          Lvl: _____
                               Code: _____

Type options, press Enter.
A=Authority U=Users 2=Edit 3=Copy 4=Delete

Opt  Role ID      Description                               Users
--  -
_   MD_ADMCMS    MDCMS Administration                       4
_   MD_ADMWF     MDWorkflow Administration                 4
_   MD_ADMXREF   MDXREF Administration                     4
_   MD_PGMR      MDCMS Programmer                         4
_   MD_PGMRADV   MD Programmer Advanced                   3
_   MD_PGMROPN   MDOpen Programmer                       3
_   MD_PROJAPR   MDCMS Authorize/Approve Involved Projects 3
_   MD_PROJEDT   MDCMS Edit Involved Projects             4
_   MD_PROJMGR   MDCMS Create/Manage all Projects         3
_   MD_RFP_SBM   MDCMS RFP Submit                         3
_   MD_RFPAPR   MDCMS RFP Approve                       3
                                          More...

F3=Exit  F4=Browse  F5=Refresh  F6=Add

```

#### Positioning and Filtering List

Pos	the cursor will be positioned to the closest match in the list
Desc	only roles that have matching text anywhere within their description will be listed
Appl	only roles with authorization to at least one code in the entered application will be listed
Lvl	only roles with authorization to at least one code in the entered level number will be listed
Code	only roles with authorization to the entered code will be listed. If application and/or level filter values are also entered, then only roles with the entered combination will be listed.
User	Only roles to which the entered user belongs will be listed

#### Fields

Role ID	A 10-Character value identifying a MDSEC Role
Description	Description of the role
Users	The number of users currently belonging to the role



Options

A user may edit the role list if their profile belongs to User Class \*SECOFR or \*SECADM or if the MDSEC Edit Auth flag is set to Y for the user.

A	View/Edit the applications and codes that the role is authorized to
U	View/Edit the list of users belonging to the role
2	Edit the description for the role
3	Copy the role to a new role. Optionally copy the authorities and or the user list to the new role.
4	Delete the role from MDSEC

**Function Keys:**

**F3=Exit** – Return to previous panel

**F4=Browse** – Browse a list of available values for a field

**F5=Refresh** – Refresh the panel

**F6=Add** – Add a new role to MDSEC. The role ID can be any 10 character value

**F12=Exit** – Return to previous panel



## 2.2 MDSEC Application Levels for Role

Option A=Authority from the MDSEC Role Listing: all Application Levels for which the role is authorized

SCCSCD	Company Name	9.03.10
SCRN1	MDSEC Application Levels for Role	18:57:01
Role: ADMIN	Administrator	
Pos: ____	Filter by Lvl: __ Desc: _____	
Type options, press Enter.		
C=Codes 4=Remove from Role 9=Apply to all Levels		
Opt	Appl	Lvl
—	md	
—	MD	90
—	OPER	10
—	WEB	80
Description		General Access
MD Product Global Authorization Codes		Y
MD Product		Y
Operations Libraries		Y
midrangedynamics.com		Y
		Bottom
F3=Exit	F5=Refresh	F6=Add

### Positioning and Filtering List

Pos	the cursor will be positioned to the first application >= entered value
Lvl	only application levels for the entered number will be listed
Desc	only application levels containing the entered value in the description will be listed

### Fields

Appl	An application defined either in MDCMS/MDXREF or from the Functional Security Codes list
Lvl	A level defined either in MDCMS/MDXREF or from the Functional Security Codes list
Description	Description of the application level
General Access	If general access (code 0) is granted to the level for the role. This allows for turning off authority for the level without removing codes for the level.

### Options

A user may only edit the list if they have \*SECOFR authority or if the MDSEC Edit Auth flag is set to Y for the user.

C	View/Edit the codes for the selected application level that the role is authorized to
4	Remove all authorizations for the application level from the role
9	Apply all code authorizations for application md to all MDCMS/MDXREF levels for the role. Option only valid for application md. The use of this option provides a rapid means to have the same authorizations regardless of the Application Level.

### Function Keys:

**F3=Exit** – Return to previous panel

**F5=Refresh** – Refresh the panel

**F6=Add** – Add a new role to MDSEC. The role ID can be any 10 character value





## 2.3 MDSEC Security Codes for Role

Option C from the MDSEC Application Levels for Role Listing: all Security Codes for which the role is authorized within the selected Application Level

SCCSCD	Company Name	9.03.10
SCRN2	MDSEC Security Codes for Role	19:21:36
Role....: MD_ADMCMS MDCMS Administration		
Appl/Lvl: md MD Product Global Authorization Codes		
Pos: ____ Filter by Desc: _____		
Type options, press Enter.		
4=Remove from Role 9=Apply to all MD Apps		
Opt	Code Description	Application Specific
-	General Access	Y
-	1 MDXREF General Product Authorization	
-	2 MDCMS General Product Authorization	
-	3 Application Group Maintenance	
-	4 Promotion Level Maintenance	Y
-	5 Attribute Maintenance	Y
-	6 Attribute Command Maintenance	Y
-	7 Object Authority Maintenance	Y
-	8 Distribution Queue Maintenance	Y
F3=Exit F5=Refresh F6=Add		More...

### Positioning and Filtering List

Pos	the cursor will be positioned to the first code >= entered value
Desc	only codes containing the entered value in the description will be listed

### Fields

Code	An application code defined either in MDCMS/MDXREF or from the Function Security Codes list to define authorization to a specific function
Description	Description of the code
Application Specific	For application md only: Y – Authorization to the MDCMS or MDXREF function will be checked against the corresponding MDCMS/MDXREF at run-time. This allows a role to have authority to one application level but not another N – Authorization to the MDCMS or MDXREF function is checked against md and there is no differentiation amongst the application levels
Limits	For non-md codes only: N – Limits not used or user is unauthorized for all checked values U – Users in role have unlimited authority to function Y – Users in role have limited authority to values between minimum and maximum



**Options**

A user may only edit the list if they have \*SECOFR authority or if the MDSEC Edit Auth flag is set to Y for the user.

L	View/Edit the limits for a non-md code
4	Remove authorization for the code from the role
9	Apply the code authorization for application md to all MDCMS/MDXREF application levels for the role. Option only valid for application <b>md</b> .

**Function Keys:**

**F3=Exit** – Return to previous panel

**F5=Refresh** – Refresh the panel

**F6=Add** – Add a new role to MDSEC. The role ID can be any 10 character value



## 2.4 MDSEC Code Limits for Role

Option L from the MDSEC Code Listing: numeric or alphanumeric value limits for an internal function security code

```

SCCSCD                               Company Name                               9.03.10
SCRN3                                MDSEC Code Limits for Role           19:36:05

Role: ADMIN      Administrator

Appl: TEST
Lvl.: 10         Test level 10
Code: 100       custom code

Numeric Limits . . . Y   Minimum Value           Maximum Value
                        _____ 55.000000   _____ 60.000000

Alphanumeric Limits . Y C _____ D _____

Valid Limit values:
  N = Limits not used or user is unauthorized for all checked values
  U = User has unlimited authority
  Y = User has limited authority to values between minimum and maximum

Enter=Confirm   F12=Previous
  
```

### Fields

Limits	N – Limits not used or user is unauthorized for all checked values U – Users in role have unlimited authority to function Y – Users in role have limited authority to values between minimum and maximum
Minimum Value	The minimum value allowed for the role at run-time, if the calling program requests that limits are checked. Not applicable for unlimited or non-limited codes
Maximum Value	The maximum value allowed for the role at run-time, if the calling program requests that limits are checked. Not applicable for unlimited or non-limited codes

### Function Keys:

**Enter=Confirm**

**F12=Previous**



## 2.5 Users with Role

Option U from the MDSEC Role Listing: all users belonging to the role

```

SCCGPD                               Company Name                9.03.10
SCRN3                                Users with Role          19:45:04

Role: APPROVER   Installation Approver

Pos: _____  Filter by Desc: _____  Ext ID: _____

Type options, press Enter.
U=User Auth  4=Remove from Role

Opt  User ID      Description                               Ext ID
_   MMORGAN      Michael Morgan                             michael
_   SD           Stephan de Diego

Bottom

F3=Exit  F5=Refresh  F6=Add

```

### Positioning and Filtering List

Pos	the cursor will be positioned to the closest match in the list
Desc	only users that have matching text anywhere within their description will be listed
Ext ID	only users that have matching text anywhere within their external ID will be listed

### Fields

User ID	The system user profile ID for the user
Description	Description of the user
Ext ID	The external ID for the user. This is used for the mapping of LDAP network user ids to the internal system ID

### Options

A user may only edit the list if they have \*SECOFR authority or if the MDSEC Edit Auth flag is set to Y for the user.

U	View all authorities for the user, based on all roles that the user belongs to
4	Remove the user from the role

### Function Keys:

**F3=Exit** – Return to previous panel

**F5=Refresh** – Refresh the panel

**F6=Add** – Add a new role to MDSEC. The role ID can be any 10 character value

**F12=Exit** – Return to previous panel



### 3 Users

#### 3.1 User Listing

Option 2 from MDSEC Menu: all users that are currently defined within MDSEC.

```

SCCUPD                               Company Name                               9.03.16
SCRN1                                 MDSEC Users                               10:37:00

          Filters:
          Name: _____ Appl/Lvl: ____ __ Code: ____
Pos: _____ Role: _____ Role, *USER   Ext ID: _____
          Grp Auth: _ Act: _ Sec: _

Type options, press Enter.
R=Roles U=User Auth 2=Edit 3=Copy 4=Delete 5=Display

Opt User ID   Name                               Role ID   Ext ID   GA Act Sec
_  BARTECH   Bartech, Roberto Munari   ADMIN    +                               N  Y  Y
_  MMORGAN   Michael Morgan            *USER    + michael  N  Y  Y
_  QSO       Secofr 2                  *USER                               Y  Y  N
_  REN       René Unternährer         ADMIN    unti      N  Y  Y
_  SD        Stephan de Diego          ADMIN    +                               Y  Y  N

                                                                 Bottom
F3=Exit  F4=Browse  F5=Refresh  F6=Add

```

#### Positioning and Filtering List

Pos	the cursor will be positioned to the first user id >= entered value
Name	only users containing the entered value in the name will be listed
Appl	only users with authorization to at least one code in the entered application will be listed
Lvl	only users with authorization to at least one code in the entered level number will be listed
Code	only users with authorization to the entered code will be listed. If application and/or level filter values are also entered, then only users with the entered combination will be listed.
Role	Only users that belong to the entered role will be listed
Ext ID	only users containing the entered value in their External User ID will be listed
Grp Auth	Filter the users based on following group authority values: Y – MDSEC Authorities based on Group Profile N – MDSEC Authorities based on User Profile B – MDSEC Authorities based on the combination of the Group Profile and User Profile
Act	Filter the users based on the following Active status values Y – the user is active and the authorizations will be granted N – the user has been disabled within MDSEC and will not have authority to any codes in MDSEC
Sec	Filter the users based on the following Security Authority values: Y – the user may make changes within MDSEC N – the user is not permitted to make changes within MDSEC

#### Fields



User ID	The user profile of a user
User Name	Name or description of the user, leave blank to retrieve from user profile, if the User ID exists as a *USRPRF object
Email Address	Email Address of the user for emailing messages or reports from MD products. Optional field.
Role ID	The role that the user belongs to. If the user belongs to multiple roles, a + will be displayed
External User ID	The external ID for the user. This is used for the mapping of LDAP network user ids to the internal system ID when logging into MDWorkflow automatically. An IBMi user profile is not required when logging in over LDAP, but will be used if it exists.
Active	If the user profile is active in MDSEC Y – the user is active and the authorizations will be granted N – the user has been disabled within MDSEC and will not have authority to any codes in MDSEC
MDSEC Edit Auth	Edit Authority within MDSEC Y – the user may make changes within MDSEC N – the user is not permitted to make changes within MDSEC
Group Profile	The group profile that the user profile belongs to. This is a read-only parameter If the User ID (first parameter) is a valid user profile, but isn't defined in MDSEC, then that user id will have any authorities that the group profile attached to the user profile has within MDSEC. If the User ID is defined in MDSEC, and is attached to a group profile, then authority will be based on the Use Group Auth parameter
Use Group Auth	If the User Profile of the User ID is attached to a Group ID, the following values are possible: Y – MDSEC Authorities based on Group Profile N – MDSEC Authorities based on User Profile B – MDSEC Authorities based on the combination of the Group Profile and User Profile
CCSID Override	The Coded Character Set to use when communicating with this system using MDOpen or MDWorkflow. This ensures that characters are displayed in the form and order that is expected for the user's locale within those clients. A value is only necessary here if the user requires a different CCSID than the CCSID defined for the system in the MDCMS system settings.
Workflow Password	The password to be used for MDWorkflow users that do not have an IBMi User Profile. This password is to be entered together with the MDSEC User ID at the MDWorkflow login prompt. If the user id exists as an IBMi user profile, then the password for the IBMi profile will be used by MDWorkflow rather than this password.
Password Expired	N – the password is not expired Y – the password is expired. The user will be prompted and required to change the password the next time that they login to MDWorkflow.



**Options**

A user may edit the user list if their profile belongs to User Class \*SECOFR or \*SECADM or if the MDSEC Edit Auth flag is set to Y for the user.

R	View/Edit the list of roles that the user belongs to
U	View all authorities for the user, based on all roles that the user belongs to
2	Edit the properties for the user. The authorities for the user are edited using option R
3	Copy the user to a new user. Optionally copy the authorities to the new user.
4	Delete the user from MDSEC
5	Display the User properties

**Function Keys:**

**F3=Exit** – Return to previous panel

**F4=Browse** – Browse a list of valid values for a field

**F5=Refresh** – Refresh the panel

**F6=Add** – Add a new user to MDSEC. If the user requires access to MDCMS or MDOpen, then the user must be a valid IBMi user profile. If only MDWorkflow access is necessary, then a User Profile does not have to exist for the ID.



### 3.2 Roles for User

Option R from the MDSEC User Listing: all roles that the user belongs to

```

SCCGPD                               Company Name          9.03.10
SCRN3                                Roles for User      21:04:58

User: MMORGAN      Michael Morgan

Pos: _____  Filter by Desc: _____

Type options, press Enter.
A=Authority  4=Remove from Role

Opt  Role      Description
_   ADMIN      Administrator
_   APPROVER    Installation Approver

Bottom

F3=Exit  F5=Refresh  F6=Add  F9=Add Personal Authorities

```

#### Positioning and Filtering List

Pos	the cursor will be positioned to the closest match in the list
Desc	only users that have matching text anywhere within their description will be listed

#### Fields

Role	A 10-Character value identifying a MDSEC Role
Description	Description of the role

#### Options

A user may only edit the list if they have \*SECOFR authority or \*SECADM authority or if the MDSEC Edit Auth flag is set to Y for the user.

A	View/Edit the application levels and codes that the role is authorized to
4	Remove the user from the role

#### Function Keys:

**F3=Exit** – Return to previous panel

**F5=Refresh** – Refresh the panel

**F6=Add** – Add 1 or more Roles for the User

**F9=Add Personal Authorities** – Add Application Level and Code authorities for a User. These can be in addition to, or instead of, Role authorities for the User





### Adding Personal User Authority

The use of the F9=Add Personal Authorities function key will enable the MDCMS administrator to add, maintain, or remove a user's personal authorities. These authorities are in addition to authorities obtained through membership in other roles.

To grant an individual personal authority to specific codes follow these steps:

1. Go to the MDSEC Main Menu
2. Select Option 2 – Users
3. Take option R=Roles for a selected user
4. Press F9=Add Personal Authorities function key (see NOTE below). On the **MDSEC Application Levels for Role** panel, press the **F6=Add** function key. On the **Unauthorized MDSEC Application Levels** panel, select all Application Levels that the user will require personal authority to and press Enter. That action will result in the Application Levels selected being returned to the **MDSEC Security Codes for Role** panel. Use the F6=Add function key to display the **Unauthorized MDSEC Codes** panel and proceed to use option 1=Select one or more Codes for each of the selected Applications. After completing the update and returning to the Roles for User panel the user will have a \*USER Role value with a Description of Personal Authorities.
5. Use the A=Authority option from the **Roles for User** panel to maintain a user's personal authority

**NOTE:** If the **F9=Add Personal Authorities** function key is not displayed on the **Roles for User** panel the user will already have a Role entry of \*USER. Once the \*USER role is created, it can be maintained using the A=Authority option from within the **Roles for User** panel.



## 4 Functional Security Codes

### 4.1 Application Level Listing

Option 3 from MDSEC Menu: all application levels to be functionally secured by MDSEC

```

SCCSBM                               Company Name          9.03.10
SCRN1                                MDSEC Administration 14:53:40

Filter by Appl: ____ Lvl: __ Desc: _____ Active: _

Type options, press Enter.
2=Edit 3=Copy 4=Delete 5=View U=Users

Opt  Appl Lvl  Description                               Active
-     md      MD Product Global Authorization Codes      Y
-     ACCT  90  Accounting application                       Y
-     INV   10  Inventory application                       Y

F3=Exit  F5=Refresh  F6=Add

Bottom
  
```

#### Filtering List

Appl	filter rows by application ID
Lvl	filter rows by level number
Desc	only levels containing the entered value in the description will be listed
Active	filter rows based on following Active values: N – Authorizations for all codes for this level have been disabled Y – Authorizations for all codes for this level are enabled

#### Fields

Appl	An application defined either in MDCMS/MDXREF or from this screen
Lvl	the application level defined either in MDCMS/MDXREF or from this screen
Description	Description of the application level
Active	N – Authorizations for all codes for this level have been disabled Y – Authorizations for all codes for this level are enabled

#### Options

A user may only edit the list if they have \*SECOFR authority or \*SECADM authority or if the MDSEC Edit Auth flag is set to Y for the user.

2	Edit the properties and codes for the application level
3	Copy the level to a new application level and optionally copy the non-md codes to the new level too
4	Remove the Application Level from MDSEC – only allowed for applications that are not managed by MDCMS or MDXREF
5	View the properties and Codes for the Application Level

#### Function Keys:



**F3=Exit** – Return to previous panel

**F5=Refresh** – Refresh the panel

**F6=Add** – Add a new Application Level to MDSEC that will not be managed by MDCMS or MDXREF



## 4.2 Application Code Listing

```

SCCSBM                               Company Name                21.04.05
SCRN2                                Edit Security Codes      17:05:09

Appl: ACCT  Lvl: 10  Desc: Accounting application                Active: Y
=====
Pos: ____   Filter by Desc: _____

Type options, press Enter.
  2=Edit  3=Copy  4=Delete  U=Users

Opt  Code Description
-    31 Insurance values
-    32 Ledger entries
-    33 VAT entries
-    34 Reverse Transactions

                                                                    Bottom

F5=Refresh  F6=Add  F12=Previous
  
```

### Positioning and Filtering List

Pos	the cursor will be positioned to the closest match in the list
Desc	only codes that have matching text anywhere within their description will be listed

### Application Fields

Appl	An application defined either in MDCMS/MDXREF or from this screen
Description	Description of the Security Code
Active	N – Authorizations for all codes for this application level have been disabled Y – Authorizations for all codes for this application level are enabled

### Code Fields

Code	A 3 digit number to identify a function to be secured. For applications that are managed by MDCMS or MDXREF, the number will be between 1 and 99 and custom codes for in-house applications must have a value between 100 and 999.
Description	Description of the code

### Options

A user may only edit the list if they have \*SECOFR authority or \*SECADM authority or if the MDSEC Edit Auth flag is set to Y for the user.

2	Edit the code description – only allowed for in-house codes
3	Copy the code to a new code for this application or to a new code in another application
4	Remove the code from MDSEC – only allowed for in-house codes

### Function Keys:

**F3=Exit** – Return to previous panel

**F5=Refresh** – Refresh the panel

**F6=Add** – Add a new Code to the Application Level. The Code must be higher than 99 if the Application is managed by MDCMS or MDXREF



## 5 Embedding MDSEC into your Applications

In order to check if a user is authorized to a function, program **MDSECAUT** is to be called. It is necessary to have library MDSEC in the library list for every job that contains a program call to MDSECAUT.

### 5.1 MDSECAUT Parameter Table

Parameter	Usage	Type	Length	Short Description
User ID	Input	String	10	User ID, *USER, blank
Application	Input	String	4	MDSEC Application Code
Level	Input	Number	2	MDSEC Application Level
Code	Input	Number	3	Security Code within Level
Return Code	Output	String	1	0=ok, 1-9=not ok
Check Numeric Value	Input	String	1	Flag for checking numeric limits
Numeric Value	Input	Number	18,6	Value to check against limits
Check Alphanumeric Value	Input	String	1	Flag for checking alphanumeric limits
Alphanumeric Value	Input	String	25	Value to check against limits

### 5.2 Detailed Description of MDSECAUT Parameters

**User ID:** Optional value to be passed to indicate which user is to be checked for authorization. If the value is \*USER or blank, MDSEC uses the job's user.

**Application:** The 4-character MDSEC code for the application that the function belongs to.

**Level:** The 2-digit MDSEC level (environment) of the application that the function belongs to. This value may be 0 if the application isn't split into multiple levels.

**Code:** The 3-digit MDSEC code within the application level that designates the function itself.

**Return Code:** The 1-character return code to tell your application whether or not the user is authorized. The values and their meaning:

0	user is authorized to function
1	user not defined in MDSEC
2	user deactivated
3	application not defined in MDSEC
4	application deactivated
5	code not defined in MDSEC
6	user not authorized
7	numeric value outside limits for user
8	alphanumeric value outside limits for user
9	system failure

**Check Numeric Value:** A flag specifying if the passed numeric value is to be checked against the authorized limits for the user. Y = check limits, N = do not check limits.

**Numeric Value:** The value to be checked against the authorized limits for the user.

**Check Alphanumeric Value:** A flag specifying if the passed alphanumeric value is to be checked against the authorized limits for the user. Y = check limits, N = do not check limits.



**Alphanumeric Value:** The value to be checked against the authorized limits for the user.

### **5.3 Programming Examples and Copybooks**

Within file QCPYSRC in library MDSEC are coding examples in COBOL, CL, RPG and ILE RPG. The examples are located in separate members all starting with EXAMP.

QCPYSRC in library MDSEC also contains copybooks for the MDSECAUT parameter data structure. Copybooks are available for the languages COBOL, RPG and ILE RPG. The copybooks are located in separate members all starting with MDSEC.



## 6 MD Command Security

Option 6 from the MDSEC Main Menu gives the user access to provide or revoke permissions to users in order to execute specific MD commands that cause updates to MDCMS data or deployments.

```

MDCCMDS                      MD Dev                      26.08.18
SCRN1                        Secured MD Commands    22:59:12

Filter by Cmd: _____ Lib: _____ Desc: _____ User: _____

Type options, press Enter.
U=Users

Opt Command  Library  Description  Authorized Users
- MDADDCMD   MDCMS   Add Command to Object Request *ALL
- MDADDREQ   MDCMS   Add Object Request *ALL
- MDADDSOG   MDCMS   Add Send Object Group *ALL
- MDCLEAR    MDCMS   Clear ALL MDCMS Activity *ALL
- MDCPYDATA  MDCMS   Copy Data between Libraries *ALL
- MDCRTOBJ   MDCMS   Create Object in Dev Library *ALL
- MDCRTSET   MDCMS   Create MD Settings Appl *ALL
- MDDELRFPP MDCMS   Delete RFPs *ALL
- MDINSRFP   MDCMS   Install RFPs *ALL
- MDLCKAMGS MDCMS   Lock Auto-Merge of Send RFPs *ALL
- MDLOCPWD   MDCMS   Change PW for MD Locations *ALL
- MDMIGMD    MDCMS   MDCMS Merge Data *ALL

More...

F3=Exit

```

When the program called by a command in this list is invoked, this table is checked to see if the job user is entitled to execute the command. If not, the program will terminate and the log entry for the command, if applicable, will be update to reflect that the job user isn't authorized.

A user can make changes to command permissions from this screen if they are registered with MDSEC Edit Authority in MDSEC.

Use option U to view/modify the list of users permitted to execute a particular command.

User special values:

\*ALL – any user on the system (including users not registered in MDSEC) can execute the command.

\*NONE – no user may execute the command



## 7 MDSEC Report Generator

Option 7 from the MDSEC Main Menu gives the user access to a variety of security reports for Users and Roles.

```

SCCRPT                               Company Name                11/26/11
SCRN1                                MDSEC Report Generator    10:07:12

Report . . . . . _          1=Role Authority
                               2=User Authority
                               3=Users with Role
                               4=Roles for User

Enter=Confirm    F7=Load Def    F11=View Output

```

Each report is customizable based on the set of criteria available for User and Role authorities to your application's functions and can be run or scheduled using the **MDRUNRPT** API.

**Function Keys:**

- F3=Exit** – Return to previous panel
- Enter=Confirm** – Confirm selection with Enter key
- F7=Load Def** – Load a saved Report Definition
- F11=View Output** – Work with MD Output





## 7.1 Role Authority

```

SCCRPT                               Company Name                11/26/11
SCRN2                                MDSEC Report Generator    10:07:12

Report . . . . . 1          MDSEC Role Authority

Include Role/User Desc . Y      Y/N
Include Appl Desc . . . . N      Y/N
Include Code Desc . . . . Y      Y/N
Sort by Auth Code . . . . Y      Y/N
Minimum Limit Info . . . . X      A=Alpha, N=Numeric, B=Both, X=Exclude
Maximum Limit Info . . . . X      A=Alpha, N=Numeric, B=Both, X=Exclude

Filter by:
User . . . . . _____ generic*
Role . . . . . _____ generic*
Application . . . . . _____ generic*
Level . . . . . _____
Code . . . . . _____
Minimum Numeric Limit . _____ .000000
Maximum Numeric Limit . _____ .000000
Minimum Alpha Limit . . _____
Maximum Alpha Limit . . _____

Enter=Confirm   F4=Browse   F9=Save Def   F11=View Output
  
```

### Criteria Selection:

Include Role/User Desc	Y – include the column for the Role or User Description in the report N – do not include
Include Appl Desc	Y – include the column Appl Description in the report N – do not include
Include Code Desc	Y – include the column Code Description in the report N – do not include
Sort by Auth Code	Y – the Application/Code is the primary sort for the report N – the Role or User is the primary sort for the report
Minimum Limit Info	A – include the column for minimum alphanumeric limits N – include the column for minimum numeric limits B – include the column for minimum alphanumeric and numeric limits X – exclude any columns for minimum limits from the report
Maximum Limit Info	A – include the column for maximum alphanumeric limits N – include the column for maximum numeric limits B – include the column for maximum alphanumeric and numeric limits X – exclude any columns for maximum limits from the report
Filter by:	
User	limit the rows to a user or users matching generic value
Role	limit the rows to a role or roles matching generic value
Application	limit the rows to an application or applications matching generic value
Level	limit the rows to a specific level
Code	limit the rows to a specific code
Minimum Numeric Limit	Limit rows to unlimited authorizations or to authorizations limited to at least the value entered
Maximum Numeric Limit	Limit rows to non-limited authorizations or to authorizations limited to no more than the value entered. If the Minimum Limit filter is also used, the



	range for the role or user must be between the minimum and maximum filter values.
Minimum Alpha Limit	Limit rows to unlimited authorizations or to authorizations limited to at least the value entered
Maximum Alpha Limit	Limit rows to non-limited authorizations or to authorizations limited to no more than the value entered. If the Minimum Limit filter is also used, the range for the role or user must be between the minimum and maximum filter values.

**Function Keys:**

**F3=Exit** – Return to previous panel

**Enter=Confirm** – Confirm selection with Enter key

**F4=Browse** – Browse a list of available values

**F9=Save Def** – Save a Report Definition

**F11=View Output** – Work with MD Output



## 7.2 User Authority

```

SCCRPT                               Company Name                11/26/11
SCRN2                                MDSEC Report Generator    10:07:12

Report . . . . . 2          MDSEC User Authority

Include Role/User Desc . Y      Y/N
Include Appl Desc . . . . N      Y/N
Include Code Desc . . . . Y      Y/N
Sort by Auth Code . . . . Y      Y/N
Minimum Limit Info . . . . X      A=Alpha, N=Numeric, B=Both, X=Exclude
Maximum Limit Info . . . . X      A=Alpha, N=Numeric, B=Both, X=Exclude

Filter by:
User . . . . . _____ generic*
Role . . . . . _____ generic*
Application . . . . . _____ generic*
Level . . . . . _____
Code . . . . . _____
Minimum Numeric Limit . _____ .000000
Maximum Numeric Limit . _____ .000000
Minimum Alpha Limit . . _____
Maximum Alpha Limit . . _____

Enter=Confirm   F4=Browse   F9=Save Def   F11=View Output
  
```

### Criteria Selection:

Include Role/User Desc	Y – include the column for the Role or User Description in the report N – do not include
Include Appl Desc	Y – include the column Appl Description in the report N – do not include
Include Code Desc	Y – include the column Code Description in the report N – do not include
Sort by Auth Code	Y – the Application/Code is the primary sort for the report N – the Role or User is the primary sort for the report
Minimum Limit Info	A – include the column for minimum alphanumeric limits N – include the column for minimum numeric limits B – include the column for minimum alphanumeric and numeric limits X – exclude any columns for minimum limits from the report
Maximum Limit Info	A – include the column for maximum alphanumeric limits N – include the column for maximum numeric limits B – include the column for maximum alphanumeric and numeric limits X – exclude any columns for maximum limits from the report
Filter by:	
User	limit the rows to a user or users matching generic value
Role	limit the rows to a role or roles matching generic value
Application	limit the rows to an application or applications matching generic value
Level	limit the rows to a specific level
Code	limit the rows to a specific code
Minimum Numeric Limit	Limit rows to unlimited authorizations or to authorizations limited to at least the value entered
Maximum Numeric Limit	Limit rows to non-limited authorizations or to authorizations limited to no more than the value entered. If the Minimum Limit filter is also used, the



	range for the role or user must be between the minimum and maximum filter values.
Minimum Alpha Limit	Limit rows to unlimited authorizations or to authorizations limited to at least the value entered
Maximum Alpha Limit	Limit rows to non-limited authorizations or to authorizations limited to no more than the value entered. If the Minimum Limit filter is also used, the range for the role or user must be between the minimum and maximum filter values.

**Function Keys:**

**F3=Exit** – Return to previous panel

**Enter=Confirm** – Confirm selection with Enter key

**F4=Browse** – Browse a list of available values

**F9=Save Def** – Save a Report Definition

**F11=View Output** – Work with MD Output



### 7.3 Users with Role

```

SCCRPT                               Company Name                               11/26/11
SCRN2                                MDSEC Report Generator                    10:07:12

Report . . . . . 3                    MDSEC Users with Role

Include Role/User Desc . Y          Y/N

Filter by:
User . . . . . _____ generic*
Role . . . . . _____ generic*

Enter=Confirm   F4=Browse   F9=Save Def   F11=View Output
  
```

**Criteria Selection:**

Include Role/User Desc	Y – include the column for the Role or User Description in the report N – do not include
Filter by:	
User	Limit the rows to a user or users matching generic value.
Role	Limit the rows to a role or roles matching generic value.

**Function Keys:**

- F3=Exit** – Return to previous panel
- Enter=Confirm** – Confirm selection with Enter key
- F4=Browse** – Browse a list of available values
- F9=Save Def** – Save a Report Definition
- F11=View Output** – Work with MD Output



## 7.4 Roles for User

```

SCCRPT                               Company Name                11/26/11
SCRN2                                MDSEC Report Generator    10:07:12

Report . . . . . 4          MDSEC Roles for User

Include Role/User Desc . Y      Y/N

Filter by:
User . . . . . _____ generic*
Role . . . . . _____ generic*

Enter=Confirm   F4=Browse   F9=Save Def   F11=View Output
  
```

### Criteria Selection:

Include Role/User Desc	Y – include the column for the Role or User Description in the report N – do not include
Filter by:	
User	Limit the rows to a user or users matching generic value.
Role	Limit the rows to a role or roles matching generic value.

### Function Keys:

- F3=Exit** – Return to previous panel
- Enter=Confirm** – Confirm selection with Enter key
- F4=Browse** – Browse a list of available values
- F9=Save Def** – Save a Report Definition
- F11=View Output** – Work with MD Output



## 7.5 Report Output

Reports (MD Output) generated within MDSEC, MDXREF and MDCMS can be viewed, printed, exported or emailed by pressing **F11** from most screens.

```

MDCOUTF          MD Production 6.1          10.03.12
SCRN1            MD Output                 17:47:05

      User      Report  Object
Filter by: MMORGAN _____

Type options, press Enter.
  3=Copy to PF  4=Delete  5=Display  6=Print  E=Export

Opt User      Date      Time      Report  Object      Library      Length Width
-  MMORGAN    24.02.11  17:36:18  PGMSRCH  MDDCLWD     MDCMST        107   80
-  MMORGAN    31.03.11   9:10:05  RFPHIST                      142   92
-  MMORGAN    14.04.11  21:34:18  LIBCOMP  MDCMS       MDCMST         28  120
-  MMORGAN    23.05.11  20:50:20  COMPARE  MDDCMSE     MDCMST        121  315
-  MMORGAN    23.05.11  20:53:01  JOURNAL  MDACST      MDADM          15  643
-  MMORGAN    23.05.11  21:01:39  PGMSRCH  MDDCMSD     MDCMST        200   80
-  MMORGAN    29.09.11   9:23:16  PROJECT                      25   92
-  MMORGAN    15.11.11  22:27:49  FLDLIST  MDDTASK     MDCMST         56  112
-  MMORGAN    22.02.12  13:42:05  JOURNAL  MDAINV      MDADM          41  130
-  MMORGAN     5.03.12  16:03:41  RFPHIST                      27   92

                                          Bottom
F3=Exit  F4=Browse  F5=Refresh  F7=Spooled Output  F17=Top  F18=Bottom

```

### Filters

Enter a value into a filter field to limit the listing to items matching the filter(s). Possible values may be selected by pressing **F4=Browse** while the cursor is positioned on the filter field.

### Options

3=Copy to PF – Copy the detail contents of the report into a formatted table (DDS Physical File). This provides a simple means to extract information out of the MD database for use in SQL, Queries or programs.

4=Delete – permanently delete the report

5=Display – view the report contents directly in the screen

6=Print – print the report contents to a spooled file

E=Export – Export the report to a CSV, PDF, TXT or XLS formatted file. The file can be placed in IFS or emailed to one or more recipients. See the parameters for command MDRUNRPT for more information.

### Function Keys:

**F4=Browse** – Browse possible values for a filter field

**F5=Refresh**

**F7=Spooled Output** – Display and manage spooled files

**F17=Top** – Position Cursor to the first entry in the list

**F18=Bottom** – Position Cursor to the last entry in the list



## 7.6 MDRUNRPT – Run Report command

Certain reports within MDSEC, MDXREF and MDCMS allow for saved report definitions to be run directly from a command line. This gives the users the ability to schedule reports to be run on a periodic basis and to have the output automatically printed or exported. This is also helpful during Project testing to allow the same parameters to be quickly used after each phase of a test.

The following screen is displayed to get the report run parameters.

```

                                Run MD Report (MDRUNRPT)

Type choices, press Enter.

Report Name . . . . . _____ COMPARE, JOURNAL, MDSEC...
User Profile . . . . . _____ User Profile
Report Definition . . . . . _____

MDCMS Instance . . . . . *DFT          *DFT, *SAME, Instance
Print result to spooled file . . *NO          *YES, *NO
Copy result to physical file . . *NO          *YES, *NO
Export result to IFS file . . . . *NO          *YES, *NO
Email result . . . . . *NO          *YES, *NO
Filename . . . . . _____

Append Timestamp to filename . . *YES         *YES, *NO
Directory . . . . . _____

Report Format . . . . . XLS           CSV, PDF, TXT, XLS
csv Field Delimiter . . . . . ', '   Field Delimiter
Address to receive Email . . . . *NONE

User to receive Email . . . . . *NONE   User ID
Group to receive Email . . . . . *NONE   Group ID

F3=Exit   F4=Prompt   F5=Refresh   F12=Cancel   F13=How to use this display
F24=More keys

```

Use **F9=All parameters** to see all available parameters for command.

### Report Name

- COMPARE – the MDXREF Data Comparison Report
- JOURNAL – the MD Journal Analysis Report
- MDSEC – the MDSEC Authorization Report
- NOTCMS – the MDCMS Audit Report listing object changes made outside of MDCMS
- PROJECT – the MDCMS Project Report
- PRJTASK – the MDCMS Project Task Report
- RFPHIST – the MDCMS Audit Report listing object changes made within MDCMS

### User Profile

The name of the user profile that defined the report definition

### Report Definition

The name of the report definition

### Print result to spooled file

- \*NO – the resulting report will not be automatically printed to a spooled file
- \*YES – the resulting report will be automatically printed to a spooled file





Copy result to physical file

- \*NO – the resulting report will not be automatically exported to a physical file
- \*YES – the resulting report will be automatically exported to a physical file (table)

Export result to IFS file

- \*NO – the resulting report will not be automatically exported to an IFS file
- \*YES – the resulting report will be automatically exported to an IFS file

Email result

- \*NO – the resulting report will not be automatically emailed to recipients
- \*YES – the resulting report will be automatically emailed to recipients

Copy to Physical file

The name of the physical file (table) to contain the detail contents of the report. Each column in the report will be placed in a separate formatted field. If the file already exists, it will be replaced.

Copy to Library

The IBM i library that is to contain the Physical file

Filename

If the results are to be exported or emailed, this is the name of the IFS file to receive the results. The file type (.CSV, .PDF, .TXT or .XLS) will be automatically appended to the end of the name.

Timestamp

- \*NO – a timestamp will not be appended to the file name
- \*YES – a timestamp in the format of YYYYMMDD\_HHMMSS will be appended to the file name

Directory

If the results are to be exported, this is the name of the IFS directory to receive the results. The directory path should begin with the root character "/".

Report Format

- CSV – the exported report will be placed in a comma separated value file which can then be opened in Microsoft excel or similar spreadsheet programs.
- PDF - the exported report will be converted to PDF. JVM 1.5 or higher is required
- TXT – the exported report will be placed in a text file with the same layout as the on-line report.
- XLS – the exported report will be converted to the excel format. JVM 1.4 or higher is required

csv Field Delimiter

The character to be used to separate fields in a csv file

Address to receive Email

A specific email address to receive the report

User to receive Email

A user id to receive the report - the address for the user will be retrieved from the MDCMS email address table.

Group to receive Email

All users for the entered group id to receive the report – this parameter requires MDWorkflow groups to be present.

## 7.7 MDEXPSPLF – Export Spooled File command

The MDEXPSPLF command provides the functionality to export any spooled file to a text or PDF file.

The following screen is displayed to get the parameters.

```

                                MD Export Spool File (MDEXPSPLF)

Type choices, press Enter.

Spool Name . . . . . _____ Spool Name
Job Name . . . . . *CURRENT   *CURRENT, Job Name
Job Number . . . . . _____ Job Number
Job User . . . . . _____ Job User
Spooled file number . . . . . *LAST   *LAST, 1-999999
MDCMS Instance . . . . . *DFT     *DFT, Instance
Format . . . . . PDF         PDF, TXT
File Name . . . . . _____

-----
Append Timestamp to filename . . *YES   *YES, *NO
Report Title . . . . . _____

-----
Page Layout . . . . . *DFT     *DFT, AUTOMATIC, LANDSCAPE
Page Size . . . . . *DFT     *DFT, A3, A4, A5, B5...
Add Page Number to each Page . . *NO    *YES, *NO
Export result to IFS file . . . > *YES   *YES, *NO
Email result . . . . . > *YES   *YES, *NO
Directory . . . . . _____
Address to receive Email . . . . *NONE
User to receive Email . . . . . *NONE   User ID
Group to receive Email . . . . . *NONE   Group ID
  
```

### Spool Name

The name of a spooled file

### Job Name

The name of the job that generated the spooled file or \*CURRENT to look for the spooled file in the current job

### Job Number

The number of the job that generated the spooled file

### Job User

The user profile of the job that generated the spooled file Report Header

### Spooled File Number

The number of the spooled file within the job or \*LAST to use the most recently generated spooled file of the given name for the given job.

### MDCMS Instance

A 1-4 character string of the suffix for an existing instance of MDXREF or \*DFT to use MDXREF

### Format

PDF – the spooled file will be converted to the PDF format. JVM 1.5 and MDCMS is required  
TXT – the spooled file will be converted to a text file



#### File Name

If the results are to be exported or emailed, this is the name of the IFS file to receive the results. The file type (.pdf or .txt) will be automatically appended to the end of the name.

#### Append Timestamp

\*NO – a timestamp will not be appended to the file name

\*YES – a timestamp in the format of YYYYMMDD\_HHMMSS will be appended to the file name

#### Report Title

The title to place in the header of the PDF file and in the subject line of the email

#### Page Layout

Values for PDF format:

\*DFT – the layout defined in data area MDSEC(instance)/MDPDFLAYOUT

AUTOMATIC – the layout is determined automatically based on the width of the spooled file

LANDSCAPE – the paper is rotated so that the wide edge is horizontal

PORTRAIT – the paper is rotated so that the wide edge is vertical

#### Page Size

Values for PDF format:

\*DFT – the size defined in data area MDSEC(instance)/MDPDFSIZE

A3, A4, A5, B5, LEGAL, LETTER

#### Add Page Number to each Page

\*NO – a page number will not be added to each page

\*YES – a page number will be added to each page in the bottom right corner

#### Export result to IFS file

\*NO – the resulting report will not be automatically exported to an IFS file

\*YES – the resulting report will be automatically exported to an IFS file

#### Email result

\*NO – the resulting report will not be automatically emailed to recipients

\*YES – the resulting report will be automatically emailed to recipients. MDCMS is required.

#### Directory

If the results are to be exported, this is the name of the IFS directory to receive the results. The directory path should begin with the root character "/".

#### Address to receive Email

A specific email address to receive the report

#### User to receive Email

A user id to receive the report - the address for the user will be retrieved from the MDCMS email address table.

#### Group to receive Email

All users for the entered group id to receive the report – this parameter requires that MDWorkflow groups are present.



## 8 Authorization Lists

### 8.1 Listing of Authorization Lists

Option 4 from MDSEC Menu: IBM i Authorization Lists to be managed by MDSEC

SCCSAL	Company Name	9.03.10
SCRN4	Authorization Lists	15:02:10
Type options, press Enter.		
2=Edit 4=Delete U=Users		
Opt List	Description	Default Authority
_ ACCT_T	Accounting Test environment	*CHANGE *EXCLUDE
_ ACCT_P	Accounting Production environment	*USE *EXCLUDE
		Bottom
F3=Exit F5=Refresh F6=Add		

#### Authorization List Options

2	Edit the description, default authority, and *PUBLIC authority for the Authorization List
4	Delete the Authorization List from MDSEC and may also optionally be removed from the IBM i system
U	View/Edit the list of user that are specified for the Authorization List

#### Function Keys:

**F3=Exit** – Return to previous panel

**F5=Refresh** – Refresh the panel

**F6=Add** – Add a new Authorization List to MDSEC/IBM i system

**F12=Exit** – Return to previous panel



## 8.2 Authorization List Maintenance

SCCSBM	MDSEC Administration	21.04.05
SCRN5	Edit List	17:08:14
Authorization List . . . .	ACCT_T	
Description . . . . .	Accounting Test environment	
Default Object Authority .	*CHANGE	
*PUBLIC Authority . . . .	*EXCLUDE	
Set Default value for existing users in Authorization List?	<u>N</u>	Y/N
Set Default value for existing users in MDSEC?	<u>N</u>	Y/N
F3=Exit F4=Browse		

### Authorization List Fields

**Description:** The description of the Authorization List object, which is stored on the IBMi System.

**Default Object Authority:** The default authority to objects for users. The default value may be applied at any time to all relevant users. The possible values are:

*ALL	complete authority to objects
*CHANGE	update authority to objects
*USE	objects may be viewed/used, but not changed
*EXCLUDE	no authority to objects
*PUBLIC	user not explicitly in list – has public authority. If user is in the List when this value is applied, then the user will be removed from the list.

**\*PUBLIC Authority:** The authority to objects for users that are not specified in the authorization list.

**Set Default value for existing users in Authorization List?:** If the answer to this question is Y (Yes), then all existing users in the Authorization List will obtain the new default authority.

**Set Default value for existing users in MDSEC?:** If the answer to this question is Y (Yes), then all existing users in the MDSEC User List will obtain the new default authority within the specific Authorization List.

### Function Keys:

**F3=Exit** – Return to previous panel

**F4=Browse** – Browse the list of possible Authority values

**F12=Exit** – Return to previous panel



### 8.3 Authorization List User Maintenance

The list of authorization lists may be modified by pressing F10 from the administration screen which is reached by pressing F9 from the initial screen within MDSEC.

```

SCCSBM                      MDSEC Administration                      21.04.05
SCRN6                        Authorization List Users                17:08:48
                               List: ASW_Q
Scan: _____ Desc Filter: _____ Authority: _____

Type options, press Enter.
4=Remove from List

Opt User      Description                               Object
  _ *PUBLIC    Authority for users not in list             *EXCLUDE
  _ PELS      Peloso Sandro                               *USE
  _ SIMJ      Simunek Jan                                *USE
  _ ORLM      Maurizio Orlando                           *USE
  _ MORM      Michael Morgan                             *USE

F3=Exit  F4=Browse  F5=Refresh  F6=Add

Bottom
  
```

#### Positioning and Filtering List

If text is entered in the Scan field, the cursor will be positioned to the closest match in the list of users. If text is entered in the Desc Filter field, only users that have matching text in their user description will be listed. For example, if MICHAEL would be entered in the above screen, only the user MORM will be displayed, because the string Michael is in the description. If an Authority value is entered in the Authority filter, then only users with the matching authority will be listed.

#### User Options

4	The "Remove from List" option will remove the user from the IBM i Authorization List. The users authority to object secured by the list will be limited to *PUBLIC authority
---	--

**Object Authority:** The authority to objects for the specific user. The possible values are:

*ALL	complete authority to objects
*CHANGE	update authority to objects
*USE	objects may be viewed/used, but not changed
*EXCLUDE	no authority to objects

#### Function Keys:

- F3=Exit** – Return to previous panel
- F4=Browse** – Browse the list of possible Authority values
- F5=Refresh** – Refresh the panel
- F6=Add** – Add a new user to the Authorization List
- F12=Exit** – Return to previous panel

## 9 DDM Security

### 9.1 Overview

DDM stands for Distributed Data Management and provides a simple means for accessing and updating data on a target IBMi system using programs running on a local IBMi system. MDCMS, for example, uses DDM for synchronizing Project and Workflow information as well as for tracking object migrations across systems.

If DDM is allowed to be used without sufficient security measures in place, then a significant risk exists that data could be read and manipulated by otherwise unauthorized persons. The DDM Security feature of MDSEC can be used to exclude unauthorized users as well as to manage which Data objects may be accessed or manipulated via DDM.

### 9.2 General Configuration

Option 5 from MDSEC Menu: DDM Security

```

SCLSDM          Company Name          9.03.10
SCRN1           DDM Security          15:47:55

DDM Filter . . . . . 1  1=Managed by MDSEC filter program
                               2=Completely unblocked
                               3=Completely blocked
                               4=Managed by another program

Log DDM Usage . . . . . Y  Y/N (entries written to MDSEC/SCDLOG)
Include MDCMS in Log . . . N  Y/N

Allow Remote Commands . . . N  Y/N

Allow DRDA (SQL) . . . . . N  Y/N

F3=Exit   F7=Data Filters   F9=User Filters   F21=Sys Command
  
```

#### Configuration Options

##### **DDM Filter**

- 1) The MDSEC DDM filter program is used as the exit point program for the DDM listener. (Network Attribute DDMACC = MDSEC/MDLDDMF)
- 2) No filtering is performed (Network Attribute DDMACC = \*OBJAUT)
- 3) DDM completely blocked (Network Attribute DDMACC = \*REJECT)
- 4) Another program is used is the exit point program for the DDM listener. It is displayed for informational purposes only and cannot be selected.

##### **Log DDM Usage**

Y – DDM transactions will be logged to file MDSEC/SCDLOG  
N – DDM transactions will not be logged



**Include MDCMS in Log**

Y – DDM transactions for files in MDCMS\* or MDXREF\* will be included in the log

N – DDM transactions for files in MDCMS\* or MDXREF\* will not be included in the log

**Allow Remote Commands**

Y – Commands sent from a remote system via DDM are allowed

N – Commands sent from a remote system via DDM are not allowed

**Allow DRDA (SQL)**

Y – Remote SQL clients using Application Requester Driver (ARD) programs are allowed access to the local database

N – Remote SQL clients using Application Requester Driver (ARD) programs are not allowed access to the local database

**Function Keys:**

**F3=Exit** – Return to previous panel

**F7=Data Filters** – Manage the list of Data Objects that may be accessed using DDM

**F9=User Filters** – Manage the list of local User Profiles that may be used to connect to the Database using DDM

**F21=Sys Command**





### 9.3 Data Filters

If the MDSEC filter program is used, the data filters are checked to see if a transaction for a particular file, data queue, or data area may take place. By default, if the library and/or object are not defined in the list, then the transaction will be blocked.

#### Field Information

##### **Library**

The name of a library on the local system

##### **Object**

The name of an object within the library or \*ALL to indicate the default allowed usage for any objects in the library that are not specifically defined in the list.

For example: ALIB/\*ALL \*UPDATE could be defined to allow updates to all data objects in library ALIB. A second entry of ALIB/AFILE \*EXCLUDE could be defined to exclude file AFILE.

##### **Usage**

\*INPUT – a DDM transaction may only view the data. Updates are not allowed.

\*UPDATE – DDM transactions may view or update the data.

\*EXCLUDE – DDM transactions are not allowed

#### Function Keys

**F3:** Return to the Configuration Screen

**F4:** Browse list of Libraries or Objects (if MDXREF is also installed)

### 9.4 User Filters

If the MDSEC filter program is used, the user filters are checked to see if the locally utilized user profile may be used to connect to the database via DDM. By default, if the user is not defined in the list, then the transaction will be blocked.

#### Field Information

##### **User**

The name of a user profile on the local system or \*ALL to indicate that any user profile may be used

#### Function Keys

**F3:** Return to the Configuration Screen

**F4:** Browse list of user profiles

## 10 System Settings

MDCSYSI	System Settings	04.09.08
SCRN1		10:37:42
Location Title . . . . .	<u>COMPANY NAME</u>	
Location ID . . . . .	<u>COMP1</u> (0-9, A-Z)	
Send Prefix . . . . .	<u>6</u> 0-9, A-Z	
Java Connect User Profile . .	MDCONNECT *NONE, Profile	
Sign Objects . . . . .	<u>Y</u> Y/N	
Default CCSID . . . . .	<u>1148</u>	
Temporary Library Prefixes:	Example <b>MDCMS ONLY</b>	
RFP Backup . . . . .	<u>SAV</u> SAV123456	
RFP Installation . . . . .	<u>CMS</u> CMS123456	
RFP Receipt . . . . .	<u>MD0</u> MD01123456	
RFP Rollback . . . . .	<u>MDR</u> MDRB123456	
MD Build Date . . . . .	4.11.10	
MD Installation Date . . . .	4.11.10	
F3=Exit	F4=Browse	

The system settings can be managed from MDSEC menu option 11.

### Location Title

The title to be displayed at the top of nearly all MD Product screens to help the user identify which system they are currently working on.

### Location ID

A 10-Character ID to uniquely identify this system. The ID for this system must match the ID defined in the OS/400 location settings for any partition that will be connecting to this system.

### Send Prefix

A 1-Character ID to uniquely identify distributions from this system. This is used to avoid conflicts in case multiple systems send Promotions to the same remote system. The temporary receiving library on the remote system will use this character in the 4<sup>th</sup> position of the library name.

### Java Connect User Profile

The technical user profile on this system to be used to run MD java modules.

Java is used in MD for Excel and PDF report generation, sending emails, and Zip compression. F4 may be used to browse user profiles.

\*NONE – java modules should not be used on this system. Recommended only if a JVM with minimum version of 1.4 is not present on the system.

### Sign Objects (MDCMS Only)

Y – Sign Objects as they are being installed to ensure that they are not manually changed during the promotion process

N – Do not sign objects. Recommended only if the necessary IBM Java Encryption Libraries are not present on the system.

#### Default CCSID (MDCMS Only)

The Coded Character Set to use by default when communicating with this system using MDOpen or MDWorkflow. This ensures that characters are displayed in the form and order that is expected for the user's locale within those clients. If certain users require a different CCSID, that value can be defined for the user in MDSEC. F4 may be used to browse the list of CCSIDs defined for use in MDCMS.

#### Temporary Library Prefixes (MDCMS Only)

The prefix string to add to the front of each type of temporary library in MDCMS. The prefix may be changed so that conflicts can be avoided when multiple instances of MDCMS exist on the same system.

#### MD Build Date

The date that this version of MD was built by Midrange Dynamics

#### MD Install Date

The date that this version of MD was installed onto this system

## **10.1 Setting the JVM to be used for MD Java Modules**

MD uses Java for various processes relating to Excel generation, PDF generation, SMTP, and Zipping. In order to carry out these processes, a JVM (minimum 1.6) must be installed on each system partition where MD will be used.

Data area MDSEC(instance)/MDJAVAHOME designates which installed JVM is to be used.

The valid values for this data area are:

\*DFT – use the default JVM

\*PROFFILE – load the JVM based on the settings in property file /mdcms/JAVA/mdcms.properties  
A pathname pointing to a JVM (for example: /QOpenSys/QIBM/ProdData/JavaVM/jdk50/32bit)

If a JVM is not available on the system, \*NONE can be specified for the Java Connect User in the System Settings (MDSEC Menu Option 11). This will disable all java-related functionality, while still allowing all MD core functionality to be performed.



## 11 Email Settings

MDCSMTP	COMPANY NAME	04.09.08
SCRN1	Email Settings	10:37:42
SMTP Hostname . . .	<u>mail.company.com</u>	
SMTP Port . . . .	<u>25</u>	
SMTP User . . . .	<u>as400@company.com</u>	
Password . . . .	_____	
Repeat Password .	_____	
email Address . .	<u>as400@company.com</u>	
SMTP Auth Reqd .	<u>Y</u> Y/N	
SMTP Logging . .	<u>Y</u> Y/N	
Encryption . . .	<u>T</u> N=None, Y=SSL, T=TLS	
ZIP Attachments .	<u>300</u> *ALWAYS, *NEVER, minimum size in KB	
MDWorkflow URL .	<u>http://company.com:8080/mdWorkflow</u>	
URL for MDOpen .	<u>Y</u> N=Never, Y=Always, I=Yes, except Interfaced Projects	
F3=Exit	F8=Addresses	F10=Log

### SMTP Hostname

The IP address or domain name of the SMTP server which will send emails to recipients

### SMTP Port

The SMTP server Port number, which normally is 25 for SMTP and 465 for SMTPS

### SMTP User

The ID of the user to connect to the SMTP server

### Password

The password for the SMTP user

### email Address

The sender address to use for the system

### SMTP Auth Reqd

Y – The SMTP Server requires user authorization to occur

N – The SMTP Server does not require user authorization to occur

### SMTP Logging

Y – Detailed debug-level SMTP information will be included in the IFS logs for service MDMAIL

N – Only high-level transaction information will be in the IFS logs for service MDMAIL

### Encryption

N – Connect to the SMTP Server in unsecured mode

Y – Connect to the SMTP Server using SSL Encryption

T – Connect to the SMTP Server using TLS Encryption

ZIP Attachments

- \*ALWAYS – attached files will be always be zipped to reduce the size of the emails
- \*NEVER – attached files will never be zipped
- n KB – an attached file will only be zipped if it is larger than the entered number of Kilobytes

MDWorkflow URL

The context path for links to the MDWorkflow application. This must include http or https, the server address, port number if not 80 and the name of the web application.

This URL is used within MDMAILF email bodies to allow the user to navigate directly to a specific RFP and is used when generating Project, Task or Subtask mails out of MDWorkflow.

URL for MDOpen

The list views for Projects, Tasks and Subtasks in MDOpen can include a URL icon. This parameter sets the priority for what the contents of the URL should be.

N – Never

Priority	URL contents
1	Interface URL to Project, Task or Subtask, if for a JIRA Project
2	First Custom URL field for the Project, Task or Subtask
3	empty

Y – Always

Priority	URL contents
1	MDWorkflow details for Project, Task or Subtask

I – Yes, except Interfaced Projects

Priority	URL contents
1	Interface URL to Project, Task or Subtask, if for a JIRA Project
2	MDWorkflow details for Project, Task or Subtask

**11.1 Email Addresses**

The email addresses of the recipients can be maintained by pressing F8 from the Email Settings screen. If DDM connections are defined, the updates will be synced to all locations.

User ID

The user profile of the user. If the user does not have a profile on the system, any other ID of up to 10 characters can be used.

Name

The Name to be recipient to be displayed in the mail header

Address

The email address of the recipient

## 11.2 Email Log

Each time the MDMAIL job is used to send an email, a log entry will be written to MDSEC file MDDEMLL with the following information:

Date, Time, Job, Recipients, Subject, Attachments and Error Message

F10 can be pressed from the Email Settings screen to view/search log entries

Additionally, the MDMAIL service logs information to the IFS which can be viewed from the Services listing.

### 11.2.1 MDSTRMAIL – Start MDMAIL Client command

In order for MDWorkflow, the MDMAIL API or the MDMAILF API to send an email, the MDMAIL SMTP client must be running. This will happen automatically if the MDMAIL service is set to start automatically. Alternatively, command MDSEC(Instance)/MDSTRMAIL can be added to a scheduled job for a fixed starting time.

#### MDSTRMAIL Parameters

Environment ID	The name of the MDCMS instance (or suffix) - *DFT refers to MDCMS being used in library MDCMS. For a different library suffix, this would be entered for the environment ID.
Submit Job	*YES – a job named MDMAIL(instance) will be submitted to the entered Job Queue *NO – the MDMAIL process will run within the current job
Job Queue	*DFT – submit to the queue defined for the MDMAIL service *JOBQ – submit to the default queue for the running job profile The name of the job queue to submit MDMAIL to
Job Queue Library	The library of the job queue to submit MDMAIL to or *LIBL if the job queue is located in the current library list
Time of Day to auto-end Job	*DFT – end at the time defined for the MDMAIL service *NEVER – the MDMAIL job shouldn't end automatically – it should run until the job is forcibly ended or command MDENDMAIL is invoked. A specific time to end in format HH:MM:SS

### 11.2.2 MDENDMAIL – End MDMAIL Client command

The MDMAIL job can be set to end automatically at a certain time, or it can be ended at any time using command MDSEC(Instance)/MDENDMAIL. Once MDENDMAIL is run, MDMAIL will cleanly stop within 30 seconds.

#### MDENDMAIL Parameters

Environment ID	The name of the MDCMS instance (or suffix) - *DFT refers to MDCMS being used in library MDCMS. For a different library suffix, this would be entered for the environment ID.
----------------	--



## Appendix A – Standard User Roles

The following table explains the primary (in **bold**) and secondary functional authorities for each role that are shipped as defaults when MDSEC is installed.

Role	Overview
MD_ADMCMS	<b>Administrative Authority</b> for all configuration settings in the <b>MDCMS</b> Setup Menu or MDOpen Settings section
MD_ADMWF	<b>Administrative Authority</b> for all settings in the <b>MDWorkflow</b> Settings Menu and corresponding Workflow settings in MDOpen
MD_ADMXREF	<b>Administrative Authority</b> for MDCMS or <b>MDXREF</b> Applications and Levels (intended when MDXREF used as Standalone product)
MD_PGMR	<b>Request to add, modify or delete Objects in MDCMS</b> (green screen). This is security code 28, which also requires that the MDCMS license key allows for as many developers as have been given access to this code within MDSEC.  Request to recompile or update Objects Retrieve Archived Source or Object Create and Edit RFPs Submit RFPs for Promotion (installation preparation step) Edit RFP in Send List Receive RFP Set involved Projects to Test-Ready Comment on involved Projects Edit involved Tasks Edit involved Subtasks
MD_PGMRADV	<b>Edit other user's Object Requests</b> Change programmer for Object Request Request Source from a different location than defined path or search template for attribute Ignore Existing Objects in other Versions Edit involved Projects Create Tasks for involved Projects Edit any Task for involved Projects Edit any Subtask for involved Tasks Merge other Users into RFP
MD_PGMROPN	<b>Request to add, modify or delete Objects in MDOpen</b> . This is security code 29, which also requires that the MDOpen license key allows for as many developers as have been given access to this code within MDSEC.  Request to recompile or update Objects Retrieve Archived Source or Object Create and Edit RFPs Submit RFPs for Promotion (installation preparation step) Edit RFP in Send List Receive RFP Set involved Projects to Test-Ready Comment on involved Projects Edit involved Tasks Edit involved Subtasks
MD_PROJAPR	<b>Confirm RFP Test Acceptance/Rejection</b> Comment on any Project View any Project Edit involved Projects <b>Authorize involved Projects</b>



MD_PROJAPR (continued)	<p><b>Approve involved Projects</b>            Comment on involved Projects            Create Tasks for involved Projects            Edit any Task for involved Projects            Edit involved Tasks            Edit any Subtask for involved Tasks            Edit involved Subtasks</p>
MD_PROJEDT	<p><b>Edit involved Projects</b>            Comment on involved Projects            Create Tasks for involved Projects            Edit any Task for involved Projects</p>
MD_PROJMGR	<p>Create and Edit RFPs  <b>Create Projects</b>            Authorize any Project            Set any Project to Test-Ready            Approve any Project            Close any Project            Comment on any Project            View any Project            Create any Task  <b>Edit any Task</b>            MDWorkflow Report Settings            Manage Time Entry for other Users            Merge other Users, Projects or Tasks into RFP</p>
MD_RFP_SBM	<p>Request to Recompile or Update Objects            Ignore Requirement to Request Related Objects            RFP Maintenance  <b>RFP Submission</b>            Receive RFP from Remote System            Set involved Projects to Test-Ready            Comment on involved Projects            Edit involved Tasks            Edit involved Subtasks</p>
MD_RFPAPR	<p>Create and Edit RFPs            Merge other Users, Projects or Tasks into RFP  <b>RFP Approval when submitted by different user</b>  <b>RFP Approval for manually changed Objects</b>            Edit RFP Reserve Date after Install  <b>RFP Approval when submitted by same user</b></p>
MD_RFPINS	<p>Create and Edit RFPs            Merge other Users, Projects or Tasks into RFP  <b>RFP Installation when approved by different user</b>            Edit RFP Reserve Date after Install            RFP Rollback            Receive RFP from Remote System  <b>RFP Installation when approved by same user</b></p>
MD_RFPSND	<p>Edit RFP in Send List  <b>Send RFP</b>            Send Data to Remote System            Close/Ignore Unsent RFP in Send List</p>
MD_USER	<p>Read-Only access to MDCMS and MDXREF</p>

**Appendix B – MD Product Security Codes**

**Column Definitions**

Code





The MDSEC Functional Security Code for MDSEC Application “md”

Appl Specific

Y – The code value for a role or user is defaulted in application md, but can be refined by the organization's MDCMS application code and level – in other words, a user may have authority to a function in application ABC, level 10 but not in application XYZ, level 10 or in application ABC, level 20.

N – The code value is in effect across all applications

Description

Describes the function for which the Code provides authorization.

Any authority granted for MDCMS is also valid for MDOpen, except for code 28.

Code 29 is only valid for MDOpen.

Administrative, RFP and Project-Specific codes are valid in MDCMS, MDOpen and MDWorkflow.

<b>Code</b>	<b>Appl Specific</b>	<b>Description</b>
1	N	Read Access to the MDXREF product
2	N	Read Access to the MDCMS product
3	N	Manage Application Codes in MDCMS (or MDXREF if MDXREF is installed without MDCMS)
4	Y	Manage Application Promotion Levels in MDCMS (or MDXREF if MDXREF is installed without MDCMS)
5	Y	Manage MDCMS Attributes
6	Y	Manage Attribute and *RFP Commands or Scripts
7	Y	Manage MDCMS Templates
8	Y	Manage Distribution Levels
9	N	Manage list of target OS/400 locations
10	N	Manage MDOpen Server Locations
11	N	Manage System Settings
12	N	Manage Email Settings
13	N	Manage Email Addresses
14	N	View MD Output generated by other Users
15	N	Delete MD Output generated by other Users
20	Y	Send Entire Application Settings to other Systems
21	Y	Send Attribute Settings to other Systems
28	Y	Request to add, modify or delete Objects in MDCMS (green screen). The use of this code also requires that the MDCMS license key allows for as many developers as have been given access to this code within MDSEC.
29	Y	Request to add, modify or delete Objects in MDOpen. The use of this code also requires that the MDOpen license key allows for as many developers as have been given access to this code within MDSEC.
30	Y	Request to recompile or update objects
31	Y	Edit or Delete the Request Records of other users
32	Y	Change the User assigned to an Object Request
33	Y	Request (check out) source from a different location than the location that MDCMS recommends to the user
34	Y	Retrieve Source or Object from the MDCMS archive
<b>Code</b>	<b>Appl Specific</b>	<b>Description</b>
35	Y	Allows ignoring the pre-submit Warning when files are changed and not all programs that access records in the file are included in the RFP



36	Y	Allow the option Ignore in the Version Conflict view for objects in a dependent level
40	Y	Create and Edit RFPs
41	Y	Submit RFP for Promotion (pre-installation step)
42	Y	Approve RFP for Installation, if RFP was submitted by different user
43	Y	Approve RFP for Installation, even if Source or Objects in the RFP were manually modified since installation into prior level. User must also have authority to code 42 or 52 depending on submit user
44	Y	Install RFP approved by different user
45	Y	Edit RFP Reserve Date in MDWorkflow after Installation complete in order to expand Installation Test window
46	Y	Confirm RFP Test Acceptance or Rejection in MDWorkflow
47	Y	Roll Back previously installed RFP
48	Y	Edit contents of RFP in Send List
49	Y	Send RFP to another System
50	Y	Send Data (*DATA/*DTAGRP requests) to another System User must also have authority to code 49
51	N	Receive RFP on target System
52	Y	Approve RFP for Installation, if RFP was submitted by same user
53	Y	Install RFP approved by same user
54	Y	Close/Ignore Unsent RFP in Send List
55	Y	Assign or Merge additional Object Requests into an RFP that doesn't already contain Object Requests for the Users assigned to the additional Requests.
56	Y	Assign or Merge additional Projects to requests in an RFP that doesn't already impact those projects.
57	Y	Assign or Merge additional Tasks for the same Project to requests in an RFP that doesn't already impact those tasks.
60	N	Create Projects
61	N	Edit any Project
62	N	Authorize work to be performed for any Project. An object can't be assigned to a project if it isn't already authorized, unless the developer has authority to this code.
63	N	Set any Project to status "Ready to Test"
64	N	Approve any Project
65	N	Close any Projects
66	N	Comment on any Project
67	N	View any Project. If not authorized to this code, only projects that the user is involved with (either directly or part of a group) will be visible.
69	N	Create a Task for any Project
70	N	Edit Tasks for any Project
71	N	Manage MDWorkflow Group Types
72	N	Manage MDWorkflow Groups
73	Y	Manage MDWorkflow Group Types Required for Test Acceptance for specific Application Levels
74	N	Manage Custom Field, Custom Status and Task Type settings for Projects or Tasks
75	N	Manage MDWorkflow Object Group settings
76	N	Manage MDWorkflow Public Report settings
77	N	Manage MDWorkflow Conflict List settings
<b>Code</b>	<b>Appl Specific</b>	<b>Description</b>
78	N	Manage Project Cost settings
81	N	Edit involved Projects
82	N	Authorize involved Projects
83	N	Set involved Projects to Test-Ready



84	N	Approve involved Projects
85	N	Close involved Projects
86	N	Comment on involved Projects
87	N	Create Tasks for involved Projects
88	N	Edit any Task for involved Projects
89	N	Edit involved Tasks
90	N	Edit any Subtask for involved Tasks
91	N	Edit involved Subtasks
92	N	Manage Time Entry for other Users